

# **HP OpenView Self-Healing Services**

## **Quick Installation & Configuration Guide**

### **ISEE Client**

**Self-Healing Services Software Version: 2.60**

**For the Following Operating Systems:  
Solaris 7, 8, 9 and 10**



**Manufacturing Part Number : None**  
**Document Release Date: January 2007**  
**Software Release Date: January 2007**

© Copyright 2003-2007 Hewlett-Packard Development Company, L.P.

---

## Legal Notices

### **Warranty.**

The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

The information contained herein is subject to change without notice.

### **Restricted Rights Legend.**

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

### **Copyright Notices.**

©Copyright 2003-2007 Hewlett-Packard Development Company, L.P.

### **Trademark Notices.**

HP-UX Release 10.20 and later and HP-UX Release 11.00 and later (in both 32- and 64-bit configurations) on all HP 9000 computers are Open Group UNIX 95 branded products.

Microsoft®, Windows®, and Windows® XP are U.S. registered trademarks of Microsoft Corporation.

UNIX® is a registered trademark of the Open Group.

Itanium® is a registered trademark of Intel Corporation or its subsidiaries in the United States and other countries.

Java™ is a U.S. trademark of Sun Microsystems, Inc.

### **Additional Notices**

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>).

---

## Conventions

The following typographical conventions are used in this guide.

Font	What the Font Represents	Example
<i>Italic</i>	Book or manual titles, and manpage names	See the <i>HP OpenView Self-Healing Services Installation guide</i> for more information.
	Provides emphasis	You <i>must</i> follow these steps.
	Specifies a variable that you must supply when entering a command	Run the command: swinstall <fileName>
	Parameters to a method	The <i>assigned_criteria</i> parameter returns an ACSE response.
<b>Bold</b>	New terms	The <b>distinguishing attribute</b> of this class...
Computer	Text and items on the computer screen	The system replies: Press Enter
	Command names	Use the grep command ...
	Method names	The get_all_replies() method does the following...
	File and directory names	Edit file /opt/hp/config/datamon.xml
	Process names	Check to see if cron is running.
	Window/dialog box names	In the Test and Track dialog...
	XML tag references	Use the <DBTable> tag to...
<b>Computer Bold</b>	Text that you must type	At the prompt, type: <b>ls -l</b>
<b>Keycap</b>	Keyboard keys	Press <b>Return</b> .
<b>Button</b>	Buttons on the user interface.	Click <b>Delete</b> .
<b>Menu Items</b>	A menu name followed by an arrow (→) means that you select the menu and then the item.	Select <b>Locate→Objects→by Comment</b>



---

## **ISEE Client Quick Install**

This guide is a quick reference for installing and configuring the HP OpenView Instant Support Enterprise Edition (ISEE) client software for a single node Self-Healing Services installation. It is not a comprehensive installation and configuration manual, and it is not intended for distributed Self-Healing Services installations.

Please see the following documents for additional details and background information, including hardware and software requirements, testing procedures, instructions for distributed installations, and troubleshooting suggestions:

*HP Self-Healing Services Installation Guide*, available at the following web address:

[http://support.openview.hp.com/pdf/selfhealing-installguide\\_ver2-6.pdf](http://support.openview.hp.com/pdf/selfhealing-installguide_ver2-6.pdf)

*HP Instant Support Enterprise Edition Client Installation and Upgrade Guide*, available at the following web address:


[ftp://ftp.hp.com/pub/services/hardware/info/isee\\_client.pdf](ftp://ftp.hp.com/pub/services/hardware/info/isee_client.pdf)

---

## Process Overview

The steps required to install and configure HP OpenView Self-Healing Services on a single system are outlined in Figure 1. The first step in this process is to install and configure the ISEE client software. This guide contains the instructions you will need to do this.

**Figure 1** Self-Healing Services Installation and Configuration Process—Single System



---

### IMPORTANT

For Solaris operating systems, it is easier to install and configure the ISEE client *before* configuring the Self-Healing Services client. For HP-UX and Windows operating systems, it is easier to install and configure the Self-Healing Services client first.

The instructions provided in this guide assume that the following things are true:

- You have root privileges on all systems on which you will install the ISEE client.
- You have an HP Passport account.
- You have a valid HP OpenView system handle or support agreement identifier (SAID).
- You have obtained the ISEE client installation package from the Self-Healing Services download web site:

[http://support.openview.hp.com/self\\_healing\\_downloads.jsp](http://support.openview.hp.com/self_healing_downloads.jsp)

---

### NOTE

If you are already using ISEE—and you have previously configured it with a valid ISEE system handle or Service Agreement Identifier (SAID)—you do not need to reinstall or reconfigure it for the purpose of Self-Healing Services.

Skip the rest of this document, and proceed directly to the *Quick Installation & Configuration Guide—Self-Healing Services Client for Solaris Operating Systems*.

## Install the ISEE Client

Follow these steps to install ISEE version A.03.50.760 (or later) on your Solaris 7, 8, 9 or 10 system:

1. Log in to the system as root.
2. To install the ISEE client software, perform the following steps:
  - a. Type the following command to extract the files in the tar file:  

```
tar -xvf ISEEPlatform.tar
```
  - b. Type the following command to execute the install script type:  

```
./install.sh
```
3. Proceed to “Configure the ISEE Client” on page 9.

---

### NOTE

After the ISEE client is installed, it will start automatically. It will also start automatically whenever you reboot the system. See “Start or Stop the ISEE Client,” on page 16 for additional information.

---

---

## Configure the ISEE Client

Follow these steps to configure the ISEE client software:

1. In a web browser, go to the following web address:

**`http://<hostname>:5060/start.html`**

where *<hostname>* is the fully qualified host name or IP address of the system on which the ISEE client is installed. This starts the ISEE user interface.

2. Enter your initial username and password:

User Name: **admin**

Password: **isee**

The following message appears:

**Figure 2**

### Initialize Message



3. Click **OK**.

The ISEE Contact Options page is displayed, as shown in Figure 3.

**Figure 3** ISEE Contact Options Page

4. Type your contact and company information. Asterisks (\*) indicate required fields.
5. In the **Server Name** field, type the name of the ISEE server for your region:

<b>Region:</b>	<b>Europe Middle East Africa</b>	<b>North/South America</b>	<b>Asia Pacific Japan</b>
<b>Server Name:</b>	isee.europe.hp.com	isee.americas.hp.com	isee.asiapac.hp.com

---

**IMPORTANT**

---

It is important to type the correct ISEE server name in this box. Once you enter this name, it cannot be changed without reinstalling the ISEE client.

6. If you will use a proxy server, provide your proxy server host name and port number. For example,

**<web\_proxy.domain>.com:80**

The proxy server login and password are required *only* if your proxy server requires user authentication.

---

**TIP**


Before submitting your information, it is useful to verify access through your proxy server. To do this, follow these steps:

- a. Open a new web browser window.
- b. Go to the following web address, where *<isee-server>* is the regional server name you entered in step 5:

**http://<isee-server>/mots/motserv**

If you successfully connect to the ISEE server in your region, you will see a page that looks like this:


**Figure 4** Page that Appears if Access is Available through Your Proxy Server



- c. Close this web browser window before proceeding.


7. In the ISEE Contact Options window, click **submit >>** to save your changes. The following message appears:

**Figure 5 ISEE Contact Information Submit Message**




8. Click **OK**. ISEE proceeds to process the information you have entered, which may take several minutes. When it is finished, the following message may appear:

**Figure 6 Updated Pages Message**



9. If this message appears, click **OK**.
10. Scroll down to the Entitlement Information section.

**Figure 7 ISEE Contact Options Page—Entitlement Information**



11. Select **Serial Number with Product number and/or Contract Identifier and Type**, as shown in Figure 7.
12. From the Contract Type list, select **System Handle**.

13. In the Contract Identifier box, type **OVSUPPORT**.

**Figure 8 ISEE Contact Options Page—Contract Information**

After you have chosen an entitlement option, enter as much of the information below as you can. If you do not have a piece of data, please leave the field blank. (Required fields are shown with asterisks. Disabled fields are shown in *italics* and "grayed out". These will not be used for entitlement, but the data will be retained for later use.)

Serial Number *	<input type="text" value="USD1234567"/>
Product Number	<input type="text"/>
Contract Identifier (Case Sensitive)	<input type="text" value="OVSUPPORT"/>
Contract Type	<input type="text" value="System Handle"/>
Compaq Software Obligation ID	<input type="text"/>

*Customers in North and Latin America with Compaq Contract ID or HP CarePack entitlement should enter their Compaq Software Obligation ID (if any) as well:*

When this form is submitted, HP will attempt to validate this contract data. An email will be sent to the Email Address specified above containing the contract data and the results of the contract lookup. The email will also show the support level to which that data entitles this system, or that the provided data was insufficient to determine a support level.

---

**NOTE**

The instructions on the Contact Options page encourage you to enter as much information as possible. For the purpose of Self-Healing Services, however, you only need to provide two pieces of information:

- Your contract type: System Handle
- Your OVSUPPORT contract identifier

Your system handle is case-sensitive. Be sure to type OVSUPPORT in upper case.


---


14. Click **submit >>**. The message shown in Figure 5 appears once again.

15. Click **OK**. After your entitlement information is successfully updated, a message such as that shown in Figure 6 may appear. If it does, click **OK**. The following message appears:

**Figure 9**



**Entitlement Verification Message**



16. Click  to close the web browser window.

---

**NOTE**

The  button has no effect in web browsers that disable this function, such as Mozilla or Firefox. Click the  button to close these browser windows.

---

**Comments**

During the installation, your notification, security, and communication options are automatically configured to the default ISEE values. No additional configuration is necessary.

**Next Steps**

After you successfully install and configure the ISEE client software, the next step is to install and configure the Self-Healing Services client software. See the following document for instructions:

[http://support.openview.hp.com/pdf/selfheal\\_quickinstall\\_solaris\\_ver2-6.pdf](http://support.openview.hp.com/pdf/selfheal_quickinstall_solaris_ver2-6.pdf)

**Additional Resources**

For additional information, including detailed instructions and troubleshooting tips, see the following documents:

*HP Self-Healing Services Installation Guide*, available at the following web address:

[http://support.openview.hp.com/pdf/selfhealing-installguide\\_ver2-6.pdf](http://support.openview.hp.com/pdf/selfhealing-installguide_ver2-6.pdf)

*HP Instant Support Enterprise Edition Client Installation and Upgrade Guide*, available at the following web address:

[ftp://ftp.hp.com/pub/services/hardware/info/isee\\_client.pdf](ftp://ftp.hp.com/pub/services/hardware/info/isee_client.pdf)

## Start or Stop the ISEE Client

To stop the ISEE client, type the following command:

```
/etc/init.d/hpservices stop
```

To restart the ISEE client, type the following command:

```
/etc/init.d/hpservices start
```

To determine whether the ISEE client is currently running, type the following command:

```
/etc/init.d/hpservices status
```